



Place the Steering Wheel




Move / Rotate the Selection



To move or rotate the selection, click the elements shown.



Copy the Selection



Sketching Tips

When drawing connected lines and arcs with the Line command, press **A** for Arc mode. Press **L** for Line mode.

To locate keypoints while sketching, use MICE shortcuts:

(M) Midpoint (I) Intersection (C) Center point (E) Endpoint

Part Tips

To display the Selection Manager, press **Shift + spacebar**, then click an object.

When making a synchronous edit, press **V** to open the Advanced Design Intent panel.

Assembly Tips

To hide a previous level, press **Ctrl + Q**.

To change Face/Part Priority, press **Ctrl + spacebar**.

Shift + drag a component from the Parts Library to drop it at the placement point and outside of the assembly workflow.

Ctrl + drag from the Parts Library to add an assembly component at the assembly origin.


To display all components in a subassembly, double-click the checkbox next to the subassembly in PathFinder.

Draft Tips

You don't have to use the Wizard to create a drawing view. You can **drag a model onto a sheet**.

To scale a drawing view before placing it, use the mouse **scroll wheel**.

To regenerate all drawing views and derived tables, press **Ctrl + Shift** while clicking **Update Views**.



Using Design Intent Relationships

When modifying a synchronous model, each shortcut turns the associated relationship on or off in the Design Intent panel.

If the relationship is not available, the shortcut does nothing.

To show or hide the Advanced Design Intent panel described here, click Advanced or use the shortcut, V.

Relationship States

Before modification



Indicates intent to maintain relationship. Click to ignore.



Indicates intent to ignore relationship. Click to maintain.

During modification



Reports that relationship is detected and maintained. Click to ignore.



Reports that relationship is detected and ignored. Click to maintain.